

TIPS

Helpful Hints when Using the Golf Handicap & Information Network®

Using TPP Clubhouse Viewer™

The TPP Clubhouse Viewer was designed to work with TPP® through the TPP RealTime™ scoring optional component. This sheet will assist you with the set-up and configuration of TPP and TPP Clubhouse Viewer.

Install TPP RealTime Optional Component

When installed, a Real Time menu option will be shown immediately before the Reports menu option on the top TPP main screen. If you do not have this option, download it using the Check for Optional Components selection under Help.

- Select <u>Help</u> -> <u>Check for Optional Components</u>.
- Click box next to **TPP RealTime Scoring Utility**.
- Click **OK**.
- After the program does its check for updates a message saying "A new update was detected and downloaded. Would you like to restart..." Click Yes.

Install the TPP Clubhouse Viewer Program

Determine a computer to run the TPP Clubhouse Viewer program which will generate the scoring screens. Get a GHIN software installation CD. Contact your golf association if you do not have a current GHIN software CD.

- Place CD in the CD tray of the computer.
- Once the Welcome Screen appears, select **Browse CD**.
- A Window will open showing the contents of the CD. Click on the **OtherGHINSoftware** folder.
- Click on the install program, **TPPClubhouse.exe**.
- When the Welcome screen appears, click **Next >**.
- When the GHIN License Agreement screen appears, click Next >.
- The Choose Destination Location screen will then appear. The default location is \GHIN\2004\TPPClubhouse; click the three dot browse button . . . to change location.
- Click Next > and the install process will begin.
- The Installation Complete screen will appear, click Finish >.
- If a message to restart the system appears, click **OK**.

Configure TPP RealTime to Create TPP Clubhouse Viewer Data File

The TPP Clubhouse Viewer program was created as an additional feature to live scoring using the TPP RealTime optional component to create and send html pages to a Website. These instructions assume you will not be creating html pages.


- Select <u>Real Time</u> -> <u>Setup Real Time Connection</u>.
 - Under Connection Method, select Use Existing Connection (LAN).
 - o Under Refresh Rate, enter 300 Seconds (5 minutes).
 - Under IP Address, enter **127.0.0.1**; which is a default id for every computer.
 - o Under Port, enter 21.
 - o The FTP Path should remain blank.
 - o The Username and Password can be set to anything, but cannot be blank.
 - o The FTP Mode should be **Passive**.
 - o Click OK.
- Select Real Time -> Select HTML Report Options.
 - For the Output Path, you can keep it to \(\frac{\GHIN\2004\TPP}{\TPP} \) or click the three dot browse button \(\ldots \cdot \text{to change location}. \) This is important, as it will be the location of the data for the TPP Clubhouse Viewer program.
 - In the HTML Report Selection section, all reports can be selected for Include to be <u>No</u>, except Stroke Play Data for TPP Club House Scoring or Match Play Data for TPP Club House Scoring, depending on type of round, needs to be set to <u>Build Only</u>.
 - The HTML Report Options section allows you to set the format of team and player names as well as any detail you would like to include.
 - o Click **OK**.
- Select <u>Real Time</u> -> <u>Specify Tournament Options</u> to select the type of scoring and the related team and or flight groups.
- Select **<u>Real Time</u>** -> **<u>Select Rounds</u>** to select the current round being scored.
- Select <u>Real Time</u> -> <u>Start/Stop Real Time Connection</u> to toggle the creation of data file for TPP Clubhouse Viewer.

Configure TPP Clubhouse Viewer Program

- By default, to start the TPP Clubhouse Viewer program, click <u>Start</u> -> <u>All Programs ></u> -> <u>GHIN</u>
 <u>Software</u> -> <u>Tournament Pairing Program 2004</u> -> <u>TPP Clubhouse Viewer</u>.
- The TPP Clubhouse Viewer menu will come up.
- Select Set TPP Clubhouse Settings.
- The TPP Clubhouse Viewer Settings screen will come up.
- Set the Data Retrieval Mode to <u>Local File</u>.
- Set the TPP Club House Stroke Play Data File to the Output Path set in the Select HTML Report Options section of TPP RealTime. Note, this can be on the same computer or in the shared folder of a networked computer.
- If the Mode is set to <u>Match Listing</u>, set the TPP Club House Match Play Data File to the Output Path set in the Select HTML Report Options section of TPP RealTime. Note, this can be on the same computer or in the shared folder of a networked computer.
- Click OK.
- Select **Launch TPP Clubhouse Viewer** to start the scoring display.
- Select **Exit Application** to end the program.

Default Layout & Configurations





USGA Layout & Configurations

